

Installation Quick Start Guide



This *Installation Quick Start Guide* provides a brief overview of the installation process. For complete details about these procedures, see the *Cloudmark Server Edition Administrator's Guide*. You can install Cloudmark Server Edition (CSE) and its Administration Console on the same host or on separate hosts.

CSE installation

System requirements

Component	Minimum Requirements
Processor	Intel Pentium or compatible, 733 megahertz (MHz) or higher
Memory	256 megabytes (MB) RAM; 512 MB recommended
Operating system	Microsoft Windows Server 2000 Microsoft Windows Server 2003 (32 or 64 bit) Microsoft Windows Server 2008 (32 or 64 bit) Microsoft Windows Small Business Server 2000 with the latest service packs installed Microsoft Windows Small Business Server 2003 (32 or 64 bit) with the latest service packs installed Microsoft Windows Small Business Server 2008 (32 or 64 bit) with the latest service packs installed
Mail server	Microsoft Exchange Server 2000, 2003, or 2007, with the latest service packs
Hard disk	20 MB for CSE software; 200 MB on the primary hard drive
Activation code	Issued by either Cloudmark or your vendor when you acquired the CSE software

Installing CSE

TO INSTALL CSE

- 1 Create a user for CSE, with an Exchange mailbox.
- 2 Add the CSE user to the Domain Admin group.
- 3 Grant Exchange Administrator rights to the CSE user, in the Exchange System Manager.
- 4 Shut down CSE, if an old instance is running.
- 5 Run the CSE installation program and follow its prompts.

If you also want to install the Administration Console on this host, select it on the Select Features screen. Otherwise, install it separately as explained at right.

- 6 If running Exchange 2007, download MAPI/CDO from Microsoft:

<http://www.microsoft.com/downloads/details.aspx?FamilyID=94274318-27c4-4d8d-9bc5-3e6484286b1f>

Install it on your Exchange server and the CSE server, if it is different than the Exchange server.

Administration Console installation

System requirements.

Component	Minimum Requirements
Processor	Intel Pentium or compatible, 733 megahertz (MHz) or higher
Memory	128 megabytes (MB) RAM
Operating system	Microsoft Windows 2000 Professional Microsoft Windows Server 2000 Microsoft Windows Server 2003 (32 or 64 bit) Microsoft Windows Server 2008 (32 or 64 bit) Microsoft Windows Small Business Server 2000) with the latest service packs installed Microsoft Windows Small Business Server 2003 (32 or 64 bit) with the latest service packs installed Microsoft Windows Small Business Server 2008 (32 or 64 bit) with the latest service packs installed Microsoft Windows XP Professional (32 or 64 bit) with the latest service packs installed
Hard disk	5 MB

Installing the Administration Console

TO INSTALL THE ADMINISTRATION CONSOLE

- 1** Run the CSE installation program and follow its prompts.
- 2** On the Select Features screen, select the Administration Console.